

# APPLICATION NOTE


## MAESTRO FIRMWARE UPDATE PROCEDURE



ALWAYS KEEP  
YOUR MAESTRO  
UP TO DATE TO  
TAKE ADVANTAGE  
OF ALL THE NEW  
FUNCTIONALITIES


### FOLLOW THIS EASY STEP-BY-STEP UPDATE PROCEDURE

1. Download the update file from the website at:  
<http://gentec-eo.com/downloads/software-firmware>  
in the [Firmware](#) tab
2. Save it to a known location on your PC (like your desktop)
3. Unzip the file:
  - 3.1 Locate the ZIP file on your computer
  - 3.2 Right-click on it and choose "Extract All..."
  - 3.3 Follow the instructions on the screen
  - 3.4 Locate the extracted folder and open it
  - 3.5 You should now see the BIN file



# APPLICATION NOTE

- Copy the BIN file on a USB key, directly in the main folder (not in a sub-folder)



- Plug the USB key in the MAESTRO

- Go to **HOME** 

- ABOUT** 

- Press the **Update** button 

- Wait for the MAESTRO to do the update sequence

- When the reboot message appears, turn off the MAESTRO

- Wait a few seconds

- Turn it on again and the update will be done

- If you want to check the update has been done, go in **HOME – About** again and verify that the firmware version corresponds to the initial update file